

# Map Viewer Installation

## ***Installing the Map Viewer from a CD***

Your installation package for the Partner Map Viewer should include a disk and user guide. Assumptions: The CD includes all the maps and necessary program files for the Map Viewer.

1. Copy the Partner subdirectory from the Map Viewer disk onto your local or hard drive (e.g., C or D drive; whichever drive has the most space) of the individual computers where the Map Viewer will be installed.
2. Double-click on the *RemoveReadOnly.bat* file located in the Partner subdirectory.
3. Create icons for the *Update.bat* and the *MapView.bat* files. To create an icon, highlight the file name, right click your mouse, select "Create Shortcut," and drag this new file to your desktop.
4. For Windows 98 users only: Right click on the *Update* icon and select "Properties." Under the "Program " tab, click in the box next to "Close on exit" to insert a checkmark.

---

## ***Installing the Map Viewer from the Network***

Assumptions: Partner Software has already installed all the maps and necessary program files on the network.

1. Create a new folder named, *Partner*, on your local or hard drive (e.g., C or D drive; whichever drive has the most space).
2. Copy the *Platform* subdirectory from the Partner Working Install on the network machine to the newly created *Partner* folder.
3. Run the *Update.bat* file located in the new *Partner\Platform\resources* folder to open the installation application. Click on "Program and Maps" to download the Map Viewer program and maps from the Map Translator Control. While running, it launches a log screen with an *Exit* button.
4. Create icons for the *Update.bat* and the *MapView.bat* files. To create an icon, highlight the file name, right click your mouse, select "Create Shortcut," and drag this new file to your desktop.
5. For Windows 98 users only: Right click on the *Update* icon and select "Properties." Under the "Program " tab, click in the box next to "Close on exit" to insert a checkmark.

---

## ***Updating the Map Viewer***

To update your Map Viewer, double click on your *Update* icon.

---

## ***Running the Map Viewer Directly from the Network***

You can run the Map Viewer directly from the network by installing a shortcut on your computer. However, this needs to be a mapped drive; it cannot just be a network neighborhood.